

Mobicents JAIN SLEE HSS Client Enabler User Guide

by Alexandre Mendonça

Preface	v
1. Document Conventions	v
1.1. Typographic Conventions	v
1.2. Pull-quote Conventions	vii
1.3. Notes and Warnings	vii
2. Provide feedback to the authors!	viii
1. Introduction to Mobicents JAIN SLEE HSS Client Enabler	1
2. Setup	3
2.1. Pre-Install Requirements and Prerequisites	3
2.1.1. Hardware Requirements	3
2.1.2. Software Prerequisites	3
2.2. Mobicents JAIN SLEE HSS Client Enabler Source Code	3
2.2.1. Release Source Code Building	3
2.2.2. Development Trunk Source Building	4
2.3. Installing Mobicents JAIN SLEE HSS Client Enabler	4
2.4. Uninstalling Mobicents JAIN SLEE HSS Client Enabler	5
3. Integrating the Mobicents JAIN SLEE HSS Client Enabler	7
3.1. The Parent's SbbLocalObject Interface	7
3.2. The Parent's Sbb Abstract Class	10
3.3. The Parent's Sbb XML Descriptor	10
4. Using the Mobicents JAIN SLEE HSS Client Enabler	13
4.1. The Child's SbbLocalObject Interface	13
4.2. Creating And Retrieving The Child Sbb	17
5. Traces and Alarms	19
5.1. Tracers	19
5.2. Alarms	19
A. Revision History	21
Index	23

Preface

1. Document Conventions

This manual uses several conventions to highlight certain words and phrases and draw attention to specific pieces of information.

In PDF and paper editions, this manual uses typefaces drawn from the [Liberation Fonts](https://fedorahosted.org/liberation-fonts/) [https://fedorahosted.org/liberation-fonts/] set. The Liberation Fonts set is also used in HTML editions if the set is installed on your system. If not, alternative but equivalent typefaces are displayed. Note: Red Hat Enterprise Linux 5 and later includes the Liberation Fonts set by default.

1.1. Typographic Conventions

Four typographic conventions are used to call attention to specific words and phrases. These conventions, and the circumstances they apply to, are as follows.

Mono-spaced Bold

Used to highlight system input, including shell commands, file names and paths. Also used to highlight key caps and key-combinations. For example:

To see the contents of the file `my_next_bestselling_novel` in your current working directory, enter the `cat my_next_bestselling_novel` command at the shell prompt and press **Enter** to execute the command.

The above includes a file name, a shell command and a key cap, all presented in Mono-spaced Bold and all distinguishable thanks to context.

Key-combinations can be distinguished from key caps by the hyphen connecting each part of a key-combination. For example:

Press **Enter** to execute the command.

Press **Ctrl+Alt+F1** to switch to the first virtual terminal. Press **Ctrl+Alt+F7** to return to your X-Windows session.

The first sentence highlights the particular key cap to press. The second highlights two sets of three key caps, each set pressed simultaneously.

If source code is discussed, class names, methods, functions, variable names and returned values mentioned within a paragraph will be presented as above, in **Mono-spaced Bold**. For example:

File-related classes include `filesystem` for file systems, `file` for files, and `dir` for directories. Each class has its own associated set of permissions.

Proportional Bold

This denotes words or phrases encountered on a system, including application names; dialogue box text; labelled buttons; check-box and radio button labels; menu titles and sub-menu titles. For example:

Choose **System > Preferences > Mouse** from the main menu bar to launch **Mouse Preferences**. In the **Buttons** tab, click the **Left-handed mouse** check box and click **Close** to switch the primary mouse button from the left to the right (making the mouse suitable for use in the left hand).

To insert a special character into a **gedit** file, choose **Applications > Accessories > Character Map** from the main menu bar. Next, choose **Search > Find** from the **Character Map** menu bar, type the name of the character in the **Search** field and click **Next**. The character you sought will be highlighted in the **Character Table**. Double-click this highlighted character to place it in the **Text to copy** field and then click the **Copy** button. Now switch back to your document and choose **Edit > Paste** from the **gedit** menu bar.

The above text includes application names; system-wide menu names and items; application-specific menu names; and buttons and text found within a GUI interface, all presented in Proportional Bold and all distinguishable by context.

Note the **>** shorthand used to indicate traversal through a menu and its sub-menus. This is to avoid the difficult-to-follow 'Select **Mouse** from the **Preferences** sub-menu in the **System** menu of the main menu bar' approach.

Mono-spaced Bold Italic Of Proportional Bold Italic

Whether Mono-spaced Bold or Proportional Bold, the addition of Italics indicates replaceable or variable text. Italics denotes text you do not input literally or displayed text that changes depending on circumstance. For example:

To connect to a remote machine using ssh, type `ssh username@domain.name` at a shell prompt. If the remote machine is `example.com` and your username on that machine is john, type `ssh john@example.com`.

The `mount -o remount file-system` command remounts the named file system. For example, to remount the `/home` file system, the command is `mount -o remount /home`.

To see the version of a currently installed package, use the `rpm -q package` command. It will return a result as follows: `package-version-release`.

Note the words in bold italics above `username`, `domain.name`, `file-system`, `package`, `version` and `release`. Each word is a placeholder, either for text you enter when issuing a command or for text displayed by the system.

Aside from standard usage for presenting the title of a work, italics denotes the first use of a new and important term. For example:

When the Apache HTTP Server accepts requests, it dispatches child processes or threads to handle them. This group of child processes or threads is known as

a *server-pool*. Under Apache HTTP Server 2.0, the responsibility for creating and maintaining these server-pools has been abstracted to a group of modules called *Multi-Processing Modules (MPMs)*. Unlike other modules, only one module from the MPM group can be loaded by the Apache HTTP Server.

1.2. Pull-quote Conventions

Two, commonly multi-line, data types are set off visually from the surrounding text.

Output sent to a terminal is set in `Mono-spaced Roman` and presented thus:

```
books      Desktop  documentation  drafts  mss    photos  stuff  svn
books_tests Desktop1  downloads      images  notes  scripts svgs
```

Source-code listings are also set in `Mono-spaced Roman` but are presented and highlighted as follows:

```
package org.jboss.book.jca.ex1;

import javax.naming.InitialContext;

public class ExClient
{
    public static void main(String args[])
        throws Exception
    {
        InitialContext iniCtx = new InitialContext();
        Object      ref  = iniCtx.lookup("EchoBean");
        EchoHome    home = (EchoHome) ref;
        Echo        echo = home.create();

        System.out.println("Created Echo");

        System.out.println("Echo.echo('Hello') = " + echo.echo("Hello"));
    }
}
```

1.3. Notes and Warnings

Finally, we use three visual styles to draw attention to information that might otherwise be overlooked.



Note

A note is a tip or shortcut or alternative approach to the task at hand. Ignoring a note should have no negative consequences, but you might miss out on a trick that makes your life easier.



Important

Important boxes detail things that are easily missed: configuration changes that only apply to the current session, or services that need restarting before an update will apply. Ignoring Important boxes won't cause data loss but may cause irritation and frustration.



Warning

A Warning should not be ignored. Ignoring warnings will most likely cause data loss.

2. Provide feedback to the authors!

If you find a typographical error in this manual, or if you have thought of a way to make this manual better, we would love to hear from you! Please submit a report in the the [Issue Tracker](http://code.google.com/p/mobicents/issues/list) [http://code.google.com/p/mobicents/issues/list], against the product **Mobicents JAIN SLEE HSS Client Enabler**, or contact the authors.

When submitting a bug report, be sure to mention the manual's identifier: JAIN_SLEE_ENABLER_HSSClient_User_Guide

If you have a suggestion for improving the documentation, try to be as specific as possible when describing it. If you have found an error, please include the section number and some of the surrounding text so we can find it easily.

Introduction to Mobicents JAIN SLEE HSS Client Enabler

The JAIN SLEE HSS Client Enabler allows JAIN SLEE Applications to interact with a Home Subscriber Server (HSS), hiding the network protocol complexity. The Enabler consists in an SBB which can be used in child relations, with a simple asynchronous interface.

The HSS is the master user database used in a IP Multimedia Subsystem (IMS) environment. It contains the subscription-related information to support the network entities actually handling calls/sessions. As an example, the HSS provides support to the call control servers in order to complete the routing/roaming procedures by solving authentication, authorisation, naming/addressing resolution, location dependencies, etc.

Setup

2.1. Pre-Install Requirements and Prerequisites

Ensure that the following requirements have been met before continuing with the install.

2.1.1. Hardware Requirements

The Enabler doesn't change the Mobicents JAIN SLEE Hardware Requirements, refer to Mobicents JAIN SLEE documentation for more information.

2.1.2. Software Prerequisites

The Enabler requires Mobicents JAIN SLEE properly set, with the Diameter Base and Sh-Client Resource Adaptors deployed.

2.2. Mobicents JAIN SLEE HSS Client Enabler Source Code

This section provides instructions on how to obtain and build the HSS Client Enabler from source code.

2.2.1. Release Source Code Building

1. Downloading the source code



Important

Subversion is used to manage its source code. Instructions for using Subversion, including install, can be found at <http://svnbook.red-bean.com>

Use SVN to checkout a specific release source, the base URL is `http://mobicents.googlecode.com/svn/tags/servers/jain-slee/2.x.y/enablers/hss-client`, then add the specific release version, lets consider 1.0.0.CR1.

```
[usr]$ svn co http://mobicents.googlecode.com/svn/tags/servers/jain-slee/2.x.y/enablers/hss-client/1.0.0.CR1 slee-enabler-hss-client-1.0.0.CR1
```

2. Building the source code



Important

Maven 2.0.9 (or higher) is used to build the release. Instructions for using Maven2, including install, can be found at <http://maven.apache.org>

Use Maven to build the deployable unit binary.

```
[usr]$ cd slee-enabler-hss-client-1.0.0.CR1
[usr]$ mvn install
```

Once the process finishes you should have the `deployable-unit` jar file in the `target` directory, if Mobicents JAIN SLEE is installed and environment variable `JBOSS_HOME` is pointing to its underlying JBoss Application Server directory, then the deployable unit jar will also be deployed in the container.



Important

This procedure does not install the Enabler's dependencies

2.2.2. Development Trunk Source Building

Similar process as for [Section 2.2.1, "Release Source Code Building"](#), the only change is the SVN source code URL, which is <http://mobicents.googlecode.com/svn/trunk/servers/jain-slee/enablers/hss-client>.

2.3. Installing Mobicents JAIN SLEE HSS Client Enabler

To install the Enabler simply execute provided ant script `build.xml` default target:

```
[usr]$ ant
```

The script will copy the Enabler's deployable unit jar to the `default` Mobicents JAIN SLEE server profile deploy directory, to deploy to another server profile use the argument `-Dnode=`.



Important

This procedure also installs the Enabler's dependencies.

2.4. Uninstalling Mobicents JAIN SLEE HSS Client Enabler

To uninstall the Enabler simply execute provided ant script `build.xml` `undeploy` target:

```
[usr]$ ant undeploy-all
```

The script will delete the Enabler's deployable unit jar from the `default` Mobicents JAIN SLEE server profile deploy directory, to undeploy from another server profile use the argument `-Dnode=`.



Important

This procedure also uninstalls the Enabler's dependencies.

Integrating the Mobicents JAIN SLEE HSS Client Enabler

This chapter explains how to setup a JAIN SLEE Service Sbb to use the Enabler.

In short terms, a Service's Sbb will define the Enabler's Sbb as a child, and to achieve that it will need to setup the XML Descriptor, Abstract Class and SbbLocalObject interface.



Important

The Service's Sbb will be referred as the Parent Sbb in the following sections.

3.1. The Parent's SbbLocalObject Interface

The Mobicents JAIN SLEE HSS Client Enabler Sbb provides asynchronous callbacks to the Parent's Sbb, and that can only be achieved if the Parent's SbbLocalObject extends a specific Java interface, deployed also by the Enabler,. The Enabler uses the Parent's SbbLocalObject when a callback to the Parent's Sbb is needed.

The SbbLocalObject which must be used or extended by the Parent's Sbb is named `org.mobicents.slee.enabler.hssclient.HSSClientParentSbbLocalObject`, which extends the `org.mobicents.slee.SbbLocalObjectExt` and `org.mobicents.slee.enabler.hssclient.HSSClientParent` interfaces, the latter declares the callbacks which must be implemented in the Parent's Sbb Abstract Class:

```
package org.mobicents.slee.enabler.hssclient;

public interface HSSClientParent {

    // Sh-Pull Operations Callbacks -----

    public void deliverRepositoryData(String publicIdentity, byte[][] serviceIndication,
        long resultCode, String data);

    public void deliverIMSPublicIdentity(String publicIdentity, byte[] msisd,
        int identitySet, long resultCode, String data);

    public void deliverIMSUserState(String publicIdentity, long resultCode, String data);

    public void deliverSCSCFName(String publicIdentity, long resultCode, String data);
```

```
public void deliverInitialFilterCriteria(String publicIdentity, String serverName,  
    long resultCode, String data);  
  
public void deliverLocationInformation(byte[] msisdn, int requestedDomain, long resultCode,  
    String data);  
  
public void deliverUserState(byte[] msisdn, int requestedDomain, long resultCode, String data);  
  
public void deliverChargingInformation(String publicIdentity, byte[] msisdn, long resultCode,  
    String data);  
  
public void deliverMSISDN(String publicIdentity, byte[] msisdn, long resultCode, String data);  
  
public void deliverPSIActivation(String publicIdentity, long resultCode, String data);  
  
// Sh-Update Operations Callbacks -----  
  
public void updateRepositoryDataResponse(String publicIdentity, long resultCode);  
  
public void updatePSIActivationResponse(String publicIdentity, long resultCode);  
  
// Sh-Subscribe Operations Callbacks -----  
  
public void subscribeRepositoryDataResponse(String publicIdentity, byte[][] serviceIndication,  
    long resultCode);  
  
public void subscribeIMSUserStateResponse(String publicIdentity, long resultCode);  
  
public void subscribeSCSCFNameResponse(String publicIdentity, long resultCode);  
  
public void subscribeInitialFilterCriteriaResponse(String publicIdentity, String serverName,  
    long resultCode);  
  
public void subscribePSIActivationResponse(String publicIdentity, long resultCode);  
  
// Sh-Notify Operations Callbacks -----  
  
public void receivedProfileUpdate(String userIdentity, byte[] msisdn, String data,  
    String originRealm, String originHost);  
  
}
```


The `deliverRepositoryData(String, byte[][], long, String)` method:
Callback from the Enabler providing the response for a request for the "Repository Data" data type.

The `deliverIMSPublicIdentity(String, byte[], int, long, String)` method:
Callback from the Enabler providing the response for a request for the "IMS Public Identity" data type.

The `deliverIMSUserState(String, long, String)` method:
Callback from the Enabler providing the response for a request for the "IMS User State" data type.

The `deliverSCSCFName(String, long, String)` method:
Callback from the Enabler providing the response for a request for the "S-CSCF Name" data type.

The `deliverInitialFilterCriteria(String, String, long, String)` method:
Callback from the Enabler providing the response for a request for the "Initial Filter Criteria" data type.

The `deliverLocationInformation(byte[], int, long, String)` method:
Callback from the Enabler providing the response for a request for the "Location Information" data type.

The `deliverUserState(byte[], int, long, String)` method:
Callback from the Enabler providing the response for a request for the "User State" data type.

The `deliverChargingInformation(String, byte[], long, String)` method:
Callback from the Enabler providing the response for a request for the "Charging Information" data type.

The `deliverMSISDN(String, byte[], long, String)` method:
Callback from the Enabler providing the response for a request for the "MSISDN" data type.

The `deliverPSIActivation(String, long, String)` method:
Callback from the Enabler providing the response for a request for the "PSI Activation" data type.

The `updateRepositoryDataResponse(String, long)` method:
Callback from the Enabler providing the response for a request to update the "Repository Data" data type.

The `updatePSIActivationResponse(String, long)` method:
Callback from the Enabler providing the response for a request to update the "PSI Activation" data type.

The `subscribeRepositoryDataResponse(String, byte[][], int, long)` method:

Callback from the Enabler providing the response for a request to subscribe/unsubscribe to the "Repository Data" data type.

The `subscribeIMSUserStateResponse(String, int, long)` method:

Callback from the Enabler providing the response for a request to subscribe/unsubscribe to the "User State" data type.

The `subscribeSCSCFNameResponse(String, int, long)` method:

Callback from the Enabler providing the response for a request to subscribe/unsubscribe to the "S-CSCF Name" data type.

The `subscribeInitialFilterCriteriaResponse(String, String, int, long)` method:

Callback from the Enabler providing the response for a request to subscribe/unsubscribe to the "Initial Filter Criteria" data type.

The `subscribePSIActivationResponse(String, int, long)` method:

Callback from the Enabler providing the response for a request to subscribe/unsubscribe to the "PSI Activation" data type.

The `receivedProfileUpdate(String, byte[], String, String, String)` method:

Callback from the Enabler providing a received Profile Update for a subscribed profile, for any data type.

3.2. The Parent's Sbb Abstract Class

The Parent Sbb Abstract Class must implement the callbacks on it's `SbbLocalObject`, that is, must implement the `org.mobicens.slee.enabler.hssclient.HSSClientParent` interface discussed in last section.

The Enabler's Sbb is a Child Sbb, and JAIN SLEE 1.1 Child Relations requires an abstract method in the Sbb Abstract Class, to retrieve the `javax.slee.ChildRelation` object, which is used to create or access specific Child Sbbs. This method should be:

```
public abstract ChildRelationExt getHSSClientChildRelation();
```

3.3. The Parent's Sbb XML Descriptor

The Parent's Sbb must define a reference to the Enabler's Child Sbb, declare which is the method name to get the related `ChildRelation` object, and also ensure the `SbbLocalObject` interface is defined correctly.

A reference to the Enabler's Child Sbb is defined right after the Parent's Sbb Vendor ID element, using the following XML element:

```
<sbb-ref>
  <sbb-name>HSSClientChildSbb</sbb-name>
  <sbb-vendor>org.mobicents</sbb-vendor>
  <sbb-version>1.0</sbb-version>
  <sbb-alias>hssClientChildSbb</sbb-alias>
</sbb-ref>
```

The method name to get the Enabler's ChildRelation object must be defined after the CMP Fields (if any), this XML element links the sbb-alias previously defined with the abstract method declared in the Parent's Sbb Abstract Class:

```
<get-child-relation-method>
  <sbb-alias-ref>hssClientChildSbb</sbb-alias-ref>
  <get-child-relation-method-name>getHSSClientChildRelation</get-child-relation-method-
name>
  <default-priority>0</default-priority>
</get-child-relation-method>
```

Finally, after the `sbb-abstract-class` element the Parent's SbbLocalObject interface name is defined:

```
<sbb-local-interface>
  <sbb-local-interface-name>...</sbb-local-interface-name>
</sbb-local-interface>
```


Using the Mobicents JAIN SLEE HSS Client Enabler

In the last chapter we integrated the Enabler in the JAIN SLEE Service's Sbb, the Parent Sbb, in this chapter it is explained how to use the Enabler's Sbb, the Child Sbb.

4.1. The Child's SbbLocalObject Interface

The Mobicents JAIN SLEE HSS Client Enabler Sbb, the Child Sbb, implements the `org.mobicents.slee.enabler.hssclient.HSSClientChildSbbLocalObject`, which extends the `org.mobicents.slee.enabler.hssclient.HSSClientChild` interfaces, the latter declares the methods which can be used to interact with the HSS:

```
package org.mobicents.slee.enabler.hssclient;

import java.io.IOException;

public interface HSSClientChild {

    // Sh-Pull Operations -----

    public String getRepositoryData(String publicIdentity, byte[][] serviceIndications,
        String destinationRealm, String destinationHost) throws IOException;

    public String getIMSPublicIdentity(String publicIdentity, byte[] msisdn, int identitySet,
        String destinationRealm, String destinationHost) throws IOException;

    public String getIMSUserState(String publicIdentity, String destinationRealm,
        String destinationHost) throws IOException;

    public String getSCSCFName(String publicIdentity, String destinationRealm, String destinationHost)
        throws IOException;

    public String getInitialFilterCriteria(String publicIdentity, String serverName,
        String destinationRealm, String destinationHost) throws IOException;

    public String getLocationInformation(byte[] msisdn, int requestedDomain, String destinationRealm,
        String destinationHost) throws IOException;

    public String getUserState(byte[] msisdn, int requestedDomain, String destinationRealm,
```

```
String destinationHost) throws IOException;

public String getChargingInformation(String publicIdentity, byte[] msisdn, String destinationRealm,
String destinationHost) throws IOException;

public String getMSISDN(String publicIdentity, byte[] msisdn, String destinationRealm,
String destinationHost) throws IOException;

public String getPSIActivation(String publicIdentity, String destinationRealm,
String destinationHost) throws IOException;

// Sh-Update Operations -----

public String updateRepositoryData(String publicIdentity, String data, String destinationRealm,
String destinationHost) throws IOException;

public String updatePSIActivation(String publicIdentity, String data, String destinationRealm,
String destinationHost) throws IOException;

// Sh-Subscribe Operations -----

public String subscribeRepositoryData(String publicIdentity, byte[][] serviceIndications,
int subscriptionRequestType, String destinationRealm, String destinationHost)
throws IOException;

public String subscribeIMSUserState(String publicIdentity, int subscriptionRequestType,
String destinationRealm, String destinationHost) throws IOException;

public String subscribeSCSCFName(String publicIdentity, int subscriptionRequestType,
String destinationRealm, String destinationHost) throws IOException;

public String subscribeInitialFilterCriteria(String publicIdentity, String serverName,
int subscriptionRequestType, String destinationRealm, String destinationHost)
throws IOException;

public String subscribePSIActivation(String publicIdentity, int subscriptionRequestType,
String destinationRealm, String destinationHost) throws IOException;

}
```

The `getRepositoryData(String, byte[][], String, String)` method:

Retrieves the "Repository Data" data type from the HSS, for the specified Public Identity and Service Indication(s). Response is provided through parent's callback `deliverRepositoryData(...)`.

The `getIMSPublicIdentity(String, byte[], int, String, String)` method:

Retrieves the "IMS Public Identity" data type from the HSS, for the specified Public Identity or MSISDN, and Identity Set. Response is provided through parent's callback `deliverIMSPublicIdentity(...)`.

The `getIMSUserState(String, String, String)` method:

Retrieves the "IMS User State" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `deliverIMSUserState(...)`.

The `org.mobicens.slee.enabler.hssclient.HSSClientChild.getSCSCFName(String, String, String)` method:

Retrieves the "S-CSCF Name" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `deliverSCSCFName(...)`.

The

`org.mobicens.slee.enabler.hssclient.HSSClientChild.getInitialFilterCriteria(String, String, String, String)` method:

Retrieves the "Initial Filter Criteria" data type from the HSS, for the specified Public Identity and Server Name. Response is provided through parent's callback `deliverInitialFilterCriteria(...)`.

The

`org.mobicens.slee.enabler.hssclient.HSSClientChild.getLocationInformation(byte[], int, String, String)` method:

Retrieves the "Location Information" data type from the HSS, for the specified MSISDN and Requested Domain. Response is provided through parent's callback `deliverLocationInformation(...)`.

The `org.mobicens.slee.enabler.hssclient.HSSClientChild.getUserState(byte[], int, String, String)` method:

Retrieves the "User State" data type from the HSS, for the specified MSISDN and Requested Domain. Response is provided through parent's callback `deliverUserState(...)`.

The

`org.mobicens.slee.enabler.hssclient.HSSClientChild.getChargingInformation(String, byte[], String, String)` method:

Retrieves the "Charging Information" data type from the HSS, for the specified Public Identity or MSISDN. Response is provided through parent's callback `deliverChargingInformation(...)`.

The `org.mobicens.slee.enabler.hssclient.HSSClientChild.getMSISDN(String, byte[], String, String)` method:

Retrieves the "MSISDN" data type from the HSS, for the specified Public Identity or MSISDN. Response is provided through parent's callback `deliverMSISDN(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.getPSIActivation(String, String, String)` method:

Retrieves the "PSI Activation" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `deliverPSIActivation(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.updateRepositoryData(String, String, String, String)` method:

Updates the "Repository Data" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `updateRepositoryDataResponse(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.updatePSIActivation(String, String, String, String)` method:

Updates the "PSI Activation" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `updatePSIActivationResponse(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.subscribeRepositoryData(String, byte[][], int, String, String)` method:

Subscribes/Unsubscribes (depending on Subscription-Request-Type value) to the "Repository Data" data type from the HSS, for the specified Public Identity and Service Indication(s). Response is provided through parent's callback `subscribeRepositoryDataResponse(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.subscribeIMSUserState(String, int, String, String)` method:

Subscribes/Unsubscribes (depending on Subscription-Request-Type value) to the "IMS User State" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `subscribeIMSUserStateResponse(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.subscribeSCSCFName(String, int, String, String)` method:

Subscribes/Unsubscribes (depending on Subscription-Request-Type value) to the "S-CSCF Name" data type from the HSS, for the specified Public Identity. Response is provided through parent's callback `subscribeSCSCFNameResponse(...)`.

The

`org.mobicents.slee.enabler.hssclient.HSSClientChild.subscribeInitialFilterCriteria(String, String, int, String, String)` method:

Subscribes/Unsubscribes (depending on Subscription-Request-Type value) to the "Initial Filter Criteria" data type from the HSS, for the specified Public Identity and Server Name. Response is provided through parent's callback `subscribeInitialFilterCriteriaResponse(...)`.

The

`org.mobicens.slee.enabler.hssclient.HSSClientChild.subscribePSIActivation(String, int, String, String)` method:

Subscribes/Unsubscribes (depending on Subscription-Request-Type value) to the "PSIActivation" data type from the HSS, for the specified Public Identity and Service Indication(s). Response is provided through parent's callback `subscribePSIActivationResponse(...)`.

4.2. Creating And Retrieving The Child Sbb

The Child Relation in the Parent Sbb Abstract Class is used to create and retrieve a Child Sbb:

```
HSSClientChildSbbLocalObject sbb = null;
// creation
try {
    sbb = (HSSClientChildSbbLocalObject) getHSSClientChildRelation().create(childName);
}
catch (Exception e) {
    tracer.severe("Failed to create child sbb", e);
}
// retrieval
try {
    sbb = (HSSClientChildSbbLocalObject) getHSSClientChildRelation().get(childName);
}
catch (Exception e) {
    tracer.severe("Failed to retrieve child sbb", e);
}
```


Traces and Alarms

5.1. Tracers



Important

Spaces were introduced in log4j category name to properly render page. Please remove them when using copy/paste.

The JAIN SLEE HSS Client Enabler uses a single JAIN SLEE 1.1 Tracer, named HSSClientChildSbb. The related log4j category is `javax.slee.SbbNotification[service=ServiceID[name=ServiceX,vendor=VendorY,version=VersionZ],sbb=SbbID[name=HSSClientChildSbb,vendor=org.mobiacents,version=1.0]]`. Where ServiceX, VendorY and VersionZ need to be replaced by the identifiers of the Service using the Enabler.

5.2. Alarms

The JAIN SLEE HSS Client Enabler does not set JAIN SLEE Alarms.

Appendix A. Revision History

Revision History

Revision 1.0

Thu Jan 06 2011

AlexandreMendonça

Creation of the Mobicents JAIN SLEE HSS Client Enabler User Guide.

Index

F

feedback, viii

